



Importing and Exporting Targets

Exporting Targets

1. Select a target you want to export from the target list.
E.g. Archival Matte




2. Click "Target settings" and select "Export" from the pull-down menu.



3. Enter a file name and click the "Save" button. The target file will be saved.

Importing Targets

1. Select a target you want to import from the target list.



2. Click "Target settings" and select "Import" from the pull-down menu.
3. Select a target file and click the "Open" button.

The file will be imported and the target will be added. Using the imported target requires the target assignment to a color mode and calibration.

See "3-8. Selecting Targets for Color Mode" (page 48) and "3-4. Calibrating the Monitor" (page 27) for details here:

<https://www.eizo.com/eizo/media/contentassets/2020/07/22/UM-03V27604K1-EN.pdf>